

Version 7.0.0

Standard allPIXAevo 32K CoaXPress

Component Versions

Variant	Version
Bitstream	23.0.0
Application/XML	14.1.0
Bootfile	16.0.0
Feature Reference	14.1.0
Gamma	KaxGamma03_10

Notes

Changes and new Features

- Use new sensor configuration to extend reset level.
 - Achieving 90,9KHz line rate

Bug Fixes

Incompatibilities

- Due to new sensor configuration it is recommended to recreate the DSNU/PRNU

Errata

- The Internal DSNU/PRNU creation may not work properly. Please check the result is good or not.
- In Master Slave Mode there may be a constant shift between the cameras
- The gain control is not working when gain control region is outside the ROI
- Led flash may not work properly
 - With some settings camera does not deliver any images
 - With some other settings there can be one pattern missing

Docs